

E-POSTER BOARD KIOSK MODE PROCESS STEPS

STEP 1: create google chrome shortcut

1. Right click on desktop -> New -> Shortcut
2. Add path to your chrome.exe (ex: "C:\Program Files (x86)\Google\Chrome\Application\chrome.exe")
3. Click 'Next'
4. Type a shortcut name (ex: e-poster board)
5. Click 'Finish'
6. Right click on it -> Properties
7. On "Target" field add at the end " --kiosk <your eposter url>" (ex: "C:\Program Files (x86)\Google\Chrome\Application\chrome.exe" --kiosk "<https://eposters.prod.stream-up.eu/config>")
8. If you double click on the shortcut this should launch your chrome in the eposter site on kiosk mode (You have to close the chrome application before doing it)

STEP 2: Set up to launch on kiosk on windows start up


1. Type 'Windows + R' or type "run" on windows search to open the run windows
2. Type 'shell:startup'
3. This should open you an explorer file
4. Move your shortcut (the one from STEP 1) in it
5. Your Windows is set up to launch the e-poster board on start up
6. On tablet mode Chrome is launch on the background (so you have to pop it up manually on the front)

STEP 3: Disable swipe edge windows 10


(<https://www.top-password.com/blog/disable-edge-swipe-gesture-in-windows-10/>)

1. Type 'Windows + R' or type "run" on windows search to open the run windows
2. Type 'gpedit.msc'
3. Navigate to: 'Computer Configuration/Administrative Templates/Windows Components/Edge UI.'

(FR: Configuration ordinateur/Composants Windows/Interface utilisateur latérale/Autoriser le balayage latérales)



4. In the right pane, double-click the on Allow edge swipe policy




5. To disable touchscreen edge swipe in Windows 10, select the Disabled option. Click Apply and then OK

6. Restart your computer to apply the changes

STEP 4: Disable left swipe to go to previous page in chrome

(<https://www.addictivetips.com/web/disable-swipe-to-go-back-in-chrome/>)

1. Open Chrome and paste the follow in the URL bar: chrome://flags/#overscroll-history-navigation
2. Open the dropdown under the "Overscroll history navigation" flag, and select "Disable" from the options.



STEP 5: Switch to tablet mode by default

1. Press 'Windows' key
2. Go to Settings (Cogs icon)
3. Click on 'System'
4. On tab, select 'Tablet mode'
5. In the first dropdown change 'Use the appropriate mode for my hardware' to 'Use tablet mode'